

Table of Contents

214	Transportation Carrier Shipment Status Message	1
GS	Functional Group Header	2
ST	Transaction Set Header	4
B10	Beginning Segment for Transportation Carrier Shipment Status Message	5
L11	Business Instructions and Reference Number	6
0100	Loop Name	7
N1	Name	8
N2	Additional Name Information	9
N3	Address Information	10
N4	Geographic Location	11
0200	Loop Assigned Number	12
LX	Assigned Number	13
0205	Loop Shipment Status Details	14
AT7	Shipment Status Details	15
MS1	Equipment, Shipment, or Real Property Location	17
MS2	Equipment or Container Owner and Type	18
Q7	Lading Exception Code	19
AT8	Shipment Weight, Packaging and Quantity Data	20
SE	Transaction Set Trailer	21
GE	Functional Group Trailer	22

214 Transportation Carrier Shipment Status Message

Functional Group=QM

Purpose: This Draft Standard for Trial Use contains the format and establishes the data contents of the Transportation Carrier Shipment Status Message Transaction Set (214) for use within the context of an Electronic Data Interchange (EDI) environment. This transaction set can be used by a transportation carrier to provide shippers, consignees, and their agents with the status of shipments in terms of dates, times, locations, route, identifying numbers, and conveyance.

Not Defined:

<u>Pos</u>	<u>Id</u>	<u>Segment Name</u>	<u>Req</u>	<u>Max Use</u>	<u>Repeat</u>	<u>Notes</u>	<u>Usage</u>
	GS	Functional Group Header	M	1			Used

Heading:

<u>Pos</u>	<u>Id</u>	<u>Segment Name</u>	<u>Req</u>	<u>Max Use</u>	<u>Repeat</u>	<u>Notes</u>	<u>Usage</u>
010	ST	Transaction Set Header	M	1			Must use
020	B10	Beginning Segment for Transportation Carrier Shipment Status Message	M	1			Must use
030	L11	Business Instructions and Reference Number	O	300			Used

<u>LOOP ID - 0100</u>					<u>10</u>		
050	N1	Name	O	1			Used
060	N2	Additional Name Information	O	1			Used
070	N3	Address Information	O	2			Used
080	N4	Geographic Location	O	1			Used

<u>LOOP ID - 0200</u>					<u>999999</u>		
130	LX	Assigned Number	O	1			Used

<u>LOOP ID - 0205</u>					<u>10</u>		
140	AT7	Shipment Status Details	O	1			Used
143	MS1	Equipment, Shipment, or Real Property Location	O	1			Used
146	MS2	Equipment or Container Owner and Type	O	1			Used
160	Q7	Lading Exception Code	O	10			Used
200	AT8	Shipment Weight, Packaging and Quantity Data	O	10			Used

610	SE	Transaction Set Trailer	M	1			Must use
-----	----	-------------------------	---	---	--	--	----------

Not Defined:

<u>Pos</u>	<u>Id</u>	<u>Segment Name</u>	<u>Req</u>	<u>Max Use</u>	<u>Repeat</u>	<u>Notes</u>	<u>Usage</u>
	GE	Functional Group Trailer	M	1			Used

GS Functional Group Header

Pos:	Max: 1
Not Defined - Mandatory	
Loop: N/A	Elements: 8

User Option (Usage): Used

Purpose: To indicate the beginning of a functional group and to provide control information

Element Summary:

<u>Ref</u>	<u>Id</u>	<u>Element Name</u>	<u>Req</u>	<u>Type</u>	<u>Min/Max</u>	<u>Usage</u>
GS01	479	Functional Identifier Code	M	ID	2/2	Must use
Description: Code identifying a group of application related transaction sets						
CodeList Summary (Total Codes: 234, Included: 1)						
Code Name						
QM Transportation Carrier Shipment Status Message (214)						
GS02	142	Application Sender's Code	M	AN	2/15	Must use
Description: Code identifying party sending transmission; codes agreed to by trading partners						
GS03	124	Application Receiver's Code	M	AN	2/15	Must use
Description: Code identifying party receiving transmission. Codes agreed to by trading partners						
GS04	373	Date	M	DT	8/8	Must use
Description: Date expressed as CCYYMMDD						
GS05	337	Time	M	TM	4/8	Must use
Description: Time expressed in 24-hour clock time as follows: HHMM, or HHMMSS, or HHMMSSD, or HHMMSSDD, where H = hours (00-23), M = minutes (00-59), S = integer seconds (00-59) and DD = decimal seconds; decimal seconds are expressed as follows: D = tenths (0-9) and DD = hundredths (00-99)						
GS06	28	Group Control Number	M	N0	1/9	Must use
Description: Assigned number originated and maintained by the sender						
GS07	455	Responsible Agency Code	M	ID	1/2	Must use
Description: Code used in conjunction with Data Element 480 to identify the issuer of the standard						
CodeList Summary (Total Codes: 2, Included: 1)						
Code Name						
X Accredited Standards Committee X12						
GS08	480	Version / Release / Industry Identifier Code	M	AN	1/12	Must use
Description: Code indicating the version, release, subrelease, and industry identifier of the EDI standard being used, including the GS and GE segments; if code in DE455 in GS segment is X, then in DE 480 positions 1-3 are the version number; positions 4-6 are the release and subrelease, level of the version; and positions 7-12 are the industry or trade association identifiers (optionally assigned by user); if code in DE455 in GS segment is T, then other formats are allowed						
CodeList Summary (Total Codes: 36, Included: 1)						
Code Name						
004010 Draft Standards Approved for Publication by ASC X12 Procedures Review Board through October 1997						

Semantics:

1. GS04 is the group date.
2. GS05 is the group time.
3. The data interchange control number GS06 in this header must be identical to the same data element in the associated functional group trailer, GE02.

Comments:

1. A functional group of related transaction sets, within the scope of X12 standards, consists of a collection of similar transaction sets enclosed by a functional group header and a functional group trailer.

ST Transaction Set Header

Pos: 010	Max: 1
Heading - Mandatory	
Loop: N/A	Elements: 2

User Option (Usage): Must use

Purpose: To indicate the start of a transaction set and to assign a control number

Element Summary:

<u>Ref</u>	<u>Id</u>	<u>Element Name</u>	<u>Req</u>	<u>Type</u>	<u>Min/Max</u>	<u>Usage</u>
ST01	143	Transaction Set Identifier Code	M	ID	3/3	Must use

Description: Code uniquely identifying a Transaction Set

CodeList Summary (Total Codes: 298, Included: 1)

Code Name

214 Transportation Carrier Shipment Status Message

ST02	329	Transaction Set Control Number	M	AN	4/9	Must use
------	-----	---------------------------------------	---	----	-----	----------

Description: Identifying control number that must be unique within the transaction set functional group assigned by the originator for a transaction set

Semantics:

1. The transaction set identifier (ST01) used by the translation routines of the interchange partners to select the appropriate transaction set definition (e.g., 810 selects the Invoice Transaction Set).

B10 Beginning Segment for Transportation Carrier Shipment Status Message

Pos: 020	Max: 1
Heading - Mandatory	
Loop: N/A	Elements: 3

User Option (Usage): Must use

Purpose: To transmit identifying numbers and other basic data relating to the transaction set

Element Summary:

<u>Ref</u>	<u>Id</u>	<u>Element Name</u>	<u>Req</u>	<u>Type</u>	<u>Min/Max</u>	<u>Usage</u>
B1001	127	Reference Identification	X	AN	1/30	Used
		Description: Reference information as defined for a particular Transaction Set or as specified by the Reference Identification Qualifier				
B1002	145	Shipment Identification Number	O	AN	1/30	Used
		Description: Identification number assigned to the shipment by the shipper that uniquely identifies the shipment from origin to ultimate destination and is not subject to modification; (Does not contain blanks or special characters)				
B1003	140	Standard Carrier Alpha Code	M	ID	2/4	Must use
		Description: Standard Carrier Alpha Code				

Syntax Rules:

1. R0106 - At least one of B1001 or B1006 is required.
2. E0105 - Only one of B1001 or B1005 may be present.
3. P0506 - If either B1005 or B1006 is present, then the other is required.

Semantics:

1. B1001 is the carrier assigned reference number.
2. B1007 indicates if the reference numbers included in this transmission were transmitted to the carrier via EDI or key entered by the carrier. A "Y" indicates that the carrier received the reference numbers in an EDI transmission; an "N" indicates that the carrier did not receive the reference numbers in an EDI transmission and key entered the data from a shipper supplied document.

Comments:

1. B1001 is the carrier's PRO (invoice number) that identifies the shipment.
2. B1003 is required when used in Transaction Set 214.
3. B1006 is the carrier assigned bar code identification or another carrier assigned shipment identification, such as a manifest number.

L11 Business Instructions and Reference Number

Pos: 030	Max: 300
Heading - Optional	
Loop: N/A	Elements: 2

User Option (Usage): Used

Purpose: To specify instructions in this business relationship or a reference number

Element Summary:

<u>Ref</u>	<u>Id</u>	<u>Element Name</u>	<u>Req</u>	<u>Type</u>	<u>Min/Max</u>	<u>Usage</u>
L1101	127	Reference Identification	X	AN	1/30	Used
		Description: Reference information as defined for a particular Transaction Set or as specified by the Reference Identification Qualifier				
L1102	128	Reference Identification Qualifier	X	ID	2/3	Used
		Description: Code qualifying the Reference Identification				
		CodeList Summary (Total Codes: 1503, Included: 1)				
		<u>Code</u> <u>Name</u>				
		PO Purchase Order Number				

Syntax Rules:

1. R0103 - At least one of L1101 or L1103 is required.
2. P0102 - If either L1101 or L1102 is present, then the other is required.

Loop Name

Pos: 050	Repeat: 10
Optional	
Loop: 0100	Elements: N/A

User Option (Usage): Used

Purpose: To identify a party by type of organization, name, and code

Loop Summary:

<u>Pos</u>	<u>Id</u>	<u>Segment Name</u>	<u>Req</u>	<u>Max Use</u>	<u>Repeat</u>	<u>Usage</u>
050	N1	Name	O	1		Used
060	N2	Additional Name Information	O	1		Used
070	N3	Address Information	O	2		Used
080	N4	Geographic Location	O	1		Used

Comments:

1. This segment, used alone, provides the most efficient method of providing organizational identification. To obtain this efficiency the "ID Code" (N104) must provide a key to the table maintained by the transaction processing party.
2. N105 and N106 further define the type of entity in N101.

N1 Name

Pos: 050	Max: 1
Heading - Optional	
Loop: 0100	Elements: 2

User Option (Usage): Used

Purpose: To identify a party by type of organization, name, and code

Element Summary:

<u>Ref</u>	<u>Id</u>	<u>Element Name</u>	<u>Req</u>	<u>Type</u>	<u>Min/Max</u>	<u>Usage</u>
N101	98	Entity Identifier Code	M	ID	2/3	Must use

Description: Code identifying an organizational entity, a physical location, property or an individual

CodeList Summary (Total Codes: 1312, Included: 2)

Code Name

CN Consignee

SH Shipper

N102	93	Name	X	AN	1/60	Used
------	----	-------------	---	----	------	------

Description: Free-form name

Syntax Rules:

1. R0203 - At least one of N102 or N103 is required.
2. P0304 - If either N103 or N104 is present, then the other is required.

Comments:

1. This segment, used alone, provides the most efficient method of providing organizational identification. To obtain this efficiency the "ID Code" (N104) must provide a key to the table maintained by the transaction processing party.
2. N105 and N106 further define the type of entity in N101.

N2 Additional Name Information

Pos: 060	Max: 1
Heading - Optional	
Loop: 0100	Elements: 1

User Option (Usage): Used

Purpose: To specify additional names or those longer than 35 characters in length

Element Summary:

<u>Ref</u>	<u>Id</u>	<u>Element Name</u>	<u>Req</u>	<u>Type</u>	<u>Min/Max</u>	<u>Usage</u>
N201	93	Name	M	AN	1/60	Must use

Description: Free-form name

N3 Address Information

Pos: 070	Max: 2
Heading - Optional	
Loop: 0100	Elements: 1

User Option (Usage): Used

Purpose: To specify the location of the named party

Element Summary:

<u>Ref</u>	<u>Id</u>	<u>Element Name</u>	<u>Req</u>	<u>Type</u>	<u>Min/Max</u>	<u>Usage</u>
N301	166	Address Information	M	AN	1/55	Must use

Description: Address information

N4 Geographic Location

Pos: 080	Max: 1
Heading - Optional	
Loop: 0100	Elements: 4

User Option (Usage): Used

Purpose: To specify the geographic place of the named party

Element Summary:

<u>Ref</u>	<u>Id</u>	<u>Element Name</u>	<u>Req</u>	<u>Type</u>	<u>Min/Max</u>	<u>Usage</u>
N401	19	City Name	O	AN	2/30	Used
		Description: Free-form text for city name				
N402	156	State or Province Code	O	ID	2/2	Used
		Description: Code (Standard State/Province) as defined by appropriate government agency				
N403	116	Postal Code	O	ID	3/15	Used
		Description: Code defining international postal zone code excluding punctuation and blanks (zip code for United States)				
N404	26	Country Code	O	ID	2/3	Used
		Description: Code identifying the country				

Syntax Rules:

1. C0605 - If N406 is present, then N405 is required.

Comments:

1. A combination of either N401 through N404, or N405 and N406 may be adequate to specify a location.
2. N402 is required only if city name (N401) is in the U.S. or Canada.

Loop Assigned Number

Pos: 130	Repeat: 999999
Optional	
Loop: 0200	Elements: N/A

User Option (Usage): Used

Purpose: To reference a line number in a transaction set

Loop Summary:

<u>Pos</u>	<u>Id</u>	<u>Segment Name</u>	<u>Req</u>	<u>Max Use</u>	<u>Repeat</u>	<u>Usage</u>
130	LX	Assigned Number	O	1		Used
140		Loop 0205	O		10	Used
160	Q7	Lading Exception Code	O	10		Used
200	AT8	Shipment Weight, Packaging and Quantity Data	O	10		Used

LX Assigned Number

Pos: 130	Max: 1
Heading - Optional	
Loop: 0200	Elements: 1

User Option (Usage): Used

Purpose: To reference a line number in a transaction set

Element Summary:

<u>Ref</u>	<u>Id</u>	<u>Element Name</u>	<u>Req</u>	<u>Type</u>	<u>Min/Max</u>	<u>Usage</u>
LX01	554	Assigned Number	M	NO	1/6	Must use

Description: Number assigned for differentiation within a transaction set

Loop Shipment Status Details

Pos: 140	Repeat: 10
Optional	
Loop: 0205	Elements: N/A

User Option (Usage): Used

Purpose: To specify the status of a shipment, the reason for that status, the date and time of the status and the date and time of any appointments scheduled.

Loop Summary:

<u>Pos</u>	<u>Id</u>	<u>Segment Name</u>	<u>Req</u>	<u>Max Use</u>	<u>Repeat</u>	<u>Usage</u>
140	AT7	Shipment Status Details	O	1		Used
143	MS1	Equipment, Shipment, or Real Property Location	O	1		Used
146	MS2	Equipment or Container Owner and Type	O	1		Used

Semantics:

1. If AT701 is present, AT705 is the date the status occurred. If AT703 is present, AT705 is a date related to an appointment.
2. If AT701 is present, AT706 is the time of the status. If AT703 is present, AT706 is the time of the appointment.
3. If AT707 is not present then AT706 represents local time of the status.

AT7 Shipment Status Details

Pos: 140	Max: 1
Heading - Optional	
Loop: 0205	Elements: 7

User Option (Usage): Used

Purpose: To specify the status of a shipment, the reason for that status, the date and time of the status and the date and time of any appointments scheduled.

Element Summary:

<u>Ref</u>	<u>Id</u>	<u>Element Name</u>	<u>Req</u>	<u>Type</u>	<u>Min/Max</u>	<u>Usage</u>
AT701	1650	Shipment Status Code	X	ID	2/2	Used

Description: Code indicating the status of a shipment

CodeList Summary (Total Codes: 42, Included: 14)

Code Name

- A7 Refused by Consignee
- AF Carrier Departed Pick-up Location with Shipment
- AG Estimated Delivery
- AH Attempted Delivery
- AJ Tendered for Delivery
- AP Delivery Not Completed
- D1 Completed Unloading at Delivery Location
- J1 Delivered to Connecting Line
- K1 Arrived at Customs
- OO Paperwork Received - Did not Receive Shipment or Equipment
- P1 Departed Terminal Location
- S1 Trailer Spotted at Consignee's Location
- SD Shipment Delayed
- X4 Arrived at Terminal Location

AT702	1651	Shipment Status or Appointment Reason Code	X	ID	2/2	Used
-------	------	---	---	----	-----	------

Description: Code indicating the reason a shipment status or appointment reason was transmitted

CodeList Summary (Total Codes: 86, Included: 1)

Code Name

- NS Normal Status

AT703	1652	Shipment Appointment Status Code	X	ID	2/2	Used
-------	------	---	---	----	-----	------

Description: Code indicating the status of an appointment to pick-up or deliver a shipment

CodeList Summary (Total Codes: 9, Included: 2)

Code Name

- AB Delivery Appointment Date and/or Time
- X9 Delivery Appointment Secured on This Date and/or Time

AT704	1651	Shipment Status or Appointment Reason Code	X	ID	2/2	Used
-------	------	---	---	----	-----	------

Description: Code indicating the reason a shipment status or appointment reason was transmitted

CodeList Summary (Total Codes: 86, Included: 1)

Code Name

- NA Normal Appointment

AT705	373	Date	X	DT	8/8	Used
-------	-----	-------------	---	----	-----	------

Description: Date expressed as CCYYMMDD

AT706	337	Time	X	TM	4/8	Used
-------	-----	-------------	---	----	-----	------

<u>Ref</u>	<u>Id</u>	<u>Element Name</u>	<u>Req</u>	<u>Type</u>	<u>Min/Max</u>	<u>Usage</u>
		Description: Time expressed in 24-hour clock time as follows: HHMM, or HHMMSS, or HHMMSSD, or HHMMSSDD, where H = hours (00-23), M = minutes (00-59), S = integer seconds (00-59) and DD = decimal seconds; decimal seconds are expressed as follows: D = tenths (0-9) and DD = hundredths (00-99)				
AT707	623	Time Code	O	ID	2/2	Used
		Description: Code identifying the time. In accordance with International Standards Organization standard 8601, time can be specified by a + or - and an indication in hours in relation to Universal Time Coordinate (UTC) time; since + is a restricted character, + and - are substituted by P and M in the codes that follow				
		CodeList Summary (Total Codes: 51, Included: 1)				
		Code Name				
		PT				Pacific Time

Syntax Rules:

1. E0103 - Only one of AT701 or AT703 may be present.
2. P0102 - If either AT701 or AT702 is present, then the other is required.
3. P0304 - If either AT703 or AT704 is present, then the other is required.
4. C0605 - If AT706 is present, then AT705 is required.
5. C0706 - If AT707 is present, then AT706 is required.

Semantics:

1. If AT701 is present, AT705 is the date the status occurred. If AT703 is present, AT705 is a date related to an appointment.
2. If AT701 is present, AT706 is the time of the status. If AT703 is present, AT706 is the time of the appointment.
3. If AT707 is not present then AT706 represents local time of the status.

MS1 Equipment, Shipment, or Real Property Location

Pos: 143	Max: 1
Heading - Optional	
Loop: 0205	Elements: 2

User Option (Usage): Used

Purpose: To specify the location of a piece of equipment, a shipment, or real property in terms of city and state or longitude and latitude

Element Summary:

<u>Ref</u>	<u>Id</u>	<u>Element Name</u>	<u>Req</u>	<u>Type</u>	<u>Min/Max</u>	<u>Usage</u>
MS101	19	City Name	X	AN	2/30	Used
		Description: Free-form text for city name				
MS102	156	State or Province Code	X	ID	2/2	Used
		Description: Code (Standard State/Province) as defined by appropriate government agency				

Syntax Rules:

1. L010203 - If MS101 is present, then at least one of MS102 or MS103 is required.
2. E0104 - Only one of MS101 or MS104 may be present.
3. C0201 - If MS102 is present, then MS101 is required.
4. C0301 - If MS103 is present, then MS101 is required.
5. P0405 - If either MS104 or MS105 is present, then the other is required.
6. C0604 - If MS106 is present, then MS104 is required.
7. C0705 - If MS107 is present, then MS105 is required.

Semantics:

1. MS104 is the longitude expressed in Degrees, Minutes, and Seconds.
2. MS105 is the latitude expressed in Degrees, Minutes, and Seconds.
3. MS106 may only be 'E' or 'W'.
4. MS107 may only be 'N' or 'S'.

MS2 Equipment or Container Owner and Type

Pos: 146	Max: 1
Heading - Optional	
Loop: 0205	Elements: 2

User Option (Usage): Used

Purpose: To specify the owner, the identification number assigned by that owner, and the type of equipment

Element Summary:

<u>Ref</u>	<u>Id</u>	<u>Element Name</u>	<u>Req</u>	<u>Type</u>	<u>Min/Max</u>	<u>Usage</u>
MS201	140	Standard Carrier Alpha Code	X	ID	2/4	Used
		Description: Standard Carrier Alpha Code				
MS202	207	Equipment Number	X	AN	1/10	Used
		Description: Sequencing or serial part of an equipment unit's identifying number (pure numeric form for equipment number is preferred)				

Syntax Rules:

1. P0102 - If either MS201 or MS202 is present, then the other is required.
2. C0402 - If MS204 is present, then MS202 is required.

Comments:

1. MS203 identifies the type for the equipment specified in MS202.

Q7 Lading Exception Code

Pos: 160	Max: 10
Heading - Optional	
Loop: 0200	Elements: 3

User Option (Usage): Used

Purpose: To specify the status of the shipment in terms of lading exception information

Element Summary:

<u>Ref</u>	<u>Id</u>	<u>Element Name</u>	<u>Req</u>	<u>Type</u>	<u>Min/Max</u>	<u>Usage</u>
Q701	33	Lading Exception Code	M	ID	1/1	Must use
Description: Code indicating the condition of the shipment						
All valid standard codes are used. (Total Codes: 6)						
Q702	211	Packaging Form Code	O	ID	3/3	Used
Description: Code for packaging form of the lading quantity						
CodeList Summary (Total Codes: 134, Included: 7)						
<u>Code</u> <u>Name</u>						
BDL Bundle						
BOX Box						
CRT Crate						
CTN Carton						
PCS Pieces						
PLT Pallet						
SKD Skid						
Q703	80	Lading Quantity	X	NO	1/7	Used
Description: Number of units (pieces) of the lading commodity						

Syntax Rules:

1. C0203 - If Q702 is present, then Q703 is required.

AT8 Shipment Weight, Packaging and Quantity Data

Pos: 200	Max: 10
Heading - Optional	
Loop: 0200	Elements: 3

User Option (Usage): Used

Purpose: To specify shipment details in terms of weight, and quantity of handling units

Element Summary:

<u>Ref</u>	<u>Id</u>	<u>Element Name</u>	<u>Req</u>	<u>Type</u>	<u>Min/Max</u>	<u>Usage</u>
AT801	187	Weight Qualifier	X	ID	1/2	Used
Description: Code defining the type of weight						
CodeList Summary (Total Codes: 51, Included: 1)						
Code Name						
G Gross Weight						
AT802	188	Weight Unit Code	X	ID	1/1	Used
Description: Code specifying the weight unit						
CodeList Summary (Total Codes: 8, Included: 1)						
Code Name						
L Pounds						
AT803	81	Weight	X	R	1/10	Used
Description: Numeric value of weight						

Syntax Rules:

1. P010203 - If either AT801, AT802 or AT803 are present, then the others are required.
2. P0607 - If either AT806 or AT807 is present, then the other is required.

Semantics:

1. AT804 is the quantity of handling units that are not unitized (for example a carton). When added to the quantity in AT805, it is the total quantity of handling units in the shipment.
2. AT805 is the quantity of handling units that are unitized (for example on a pallet or slip sheet). When added to the quantity in AT804 it is the total quantity of handling units for the shipment.

SE Transaction Set Trailer

Pos: 610	Max: 1
Heading - Mandatory	
Loop: N/A	Elements: 2

User Option (Usage): Must use

Purpose: To indicate the end of the transaction set and provide the count of the transmitted segments (including the beginning (ST) and ending (SE) segments)

Element Summary:

<u>Ref</u>	<u>Id</u>	<u>Element Name</u>	<u>Req</u>	<u>Type</u>	<u>Min/Max</u>	<u>Usage</u>
SE01	96	Number of Included Segments	M	NO	1/10	Must use
Description: Total number of segments included in a transaction set including ST and SE segments						
SE02	329	Transaction Set Control Number	M	AN	4/9	Must use
Description: Identifying control number that must be unique within the transaction set functional group assigned by the originator for a transaction set						

Comments:

1. SE is the last segment of each transaction set.

GE Functional Group Trailer

Pos:	Max: 1
Not Defined - Mandatory	
Loop: N/A	Elements: 2

User Option (Usage): Used

Purpose: To indicate the end of a functional group and to provide control information

Element Summary:

<u>Ref</u>	<u>Id</u>	<u>Element Name</u>	<u>Req</u>	<u>Type</u>	<u>Min/Max</u>	<u>Usage</u>
GE01	97	Number of Transaction Sets Included	M	NO	1/6	Must use
Description: Total number of transaction sets included in the functional group or interchange (transmission) group terminated by the trailer containing this data element						
GE02	28	Group Control Number	M	NO	1/9	Must use
Description: Assigned number originated and maintained by the sender						

Semantics:

1. The data interchange control number GE02 in this trailer must be identical to the same data element in the associated functional group header, GS06.

Comments:

1. The use of identical data interchange control numbers in the associated functional group header and trailer is designed to maximize functional group integrity. The control number is the same as that used in the corresponding header.